

Application Support Documentation

PAUSIT 2.0.1 FOR WINDOWS



Documentation version: 2018-06-11

Contents

System requirements	3
Hardware and software requirements.....	3
VDI requirements	3
License activation requirements	3
Installation.....	3
Prerequisites.....	3
Registry permissions.....	3
Installation folder permissions	3
User settings folder permissions	4
Installing the application	4
Manual installation.....	4
Automated installation.....	4
Uninstallation	4
Manual uninstallation	4
Automated uninstallation	4
FAQ.....	5
Where is the license file located?	5
Where are the user settings saved?.....	5
Where are the log files saved?	5
Log file for scheduler	5
Log file for player and settings	5
Manual.....	5

System requirements

Hardware and software requirements

Pausit for Windows is built using the Microsoft .NET-platform and contains a component for rendering of 3D content created with Unity3D.

- Windows Vista SP1 or later
- .NET 4.5 runtime
- GPU with DX10 (SM 4.0)
- CPU with SSE2 instruction set
- 250 MB available disk space

VDI requirements

Pausit for Windows can run in a VDI environment. The application requires that the VDI environment has hardware accelerated 3D-support enabled.

License activation requirements

Pausit for Windows requires an open port to the Internet for online activation:

```
TCP port 443 activate.pausit.se
```

The license will be activated on a recurring schedule.

Installation

Pausit for Windows is packaged in a Windows Installer Database (MSI file) using WiX. The installer is signed using a code-signing certificate.

Pausit for Windows can be installed per-machine (all users) or per-user (current user executing the installation). A per-machine installation requires elevated permissions.

Prerequisites

Registry permissions

The installer needs permissions to write to the registry to be able to add Pausit to auto run at a registry path.

For “All Users” installation:

```
HKLM\SOFTWARE\WOW6432Node\Microsoft\Windows\CurrentVersion\Run
```

For “Current User” installation:

```
HKCU\Software\Microsoft\Windows\CurrentVersion\Run
```

Installation folder permissions

The installer needs permissions to write application files to the installation folder. Default installation paths for Pausit is dependent on the user context.

For “All Users” installation :

```
C:\Program Files (x86)\Pausit
```

For “Current User” installation:

```
%LocalAppData%\Apps\Pausit
```

User settings folder permissions

Pausit for Windows must have read and write permissions on the following directory:

```
%AppData%\Pausit
```

Installing the application

The application can be installed manually by the end user through a graphical interface, or automatically with no user input required. Windows Installer packages are supported by most deployment tools like SCCM, CA Unicenter, IBM's Tivoli, Altiris Client Management Suite, and several others.

Manual installation

Locate the Pausit for Windows installation file, "Pausit.msi". Make sure there is a valid license file named "Pausit.lic" included in the same directory as the installation file.

Start the installation by double clicking the installation file and follow the instructions in the guide.

Automated installation

Pausit for Windows can be installed with Windows Installer, using the command line utility "msiexec". There are a number of command line options available, see the link below. To perform a standard, per-machine, unattended installation of Pausit for Windows, execute the following command:

```
msiexec /i Pausit.msi /q
```

To install Pausit for the current user, execute the following command:

```
msiexec /i Pausit.msi /q MSIINSTALLPERUSER=1
```

More configurations can be made to the installer, see "Command-Line Options for Windows Installer" at the link below:

[https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988(v=vs.85).aspx)

NOTE: If Pausit version 1 is installed it has to be uninstalled before installing version 2 or the installation will fail. For manual installation version 1 will be uninstalled by the installer.

Uninstallation

Manual uninstallation

Pausit for Windows can be uninstalled manually via the "Programs and Features" section of the Windows Control Panel, or the "Uninstall Pausit" shortcut in the Start Menu.

Automated uninstallation

Pausit for Windows can be uninstalled with Windows Installer, using the command line utility "msiexec". An uninstallation with Windows Installer requires the original installation package (MSI file) or the Pausit for Windows product code. To perform a standard, unattended uninstallation of Pausit for Windows using the original installation package, execute the following command:

```
msiexec /x Pausit.msi /q
```

FAQ

Where is the license file located?

The license file for Pausit for Windows is initially copied to the installation directory. When a user launches Pausit for the first time, the license is also copied to the following file:

```
%AppData%\Pausit\Pausit.lic
```

Where are the user settings saved?

The user settings for Pausit for Windows is saved in the following SQLite3 database file:

```
%AppData%\Pausit\Pausit.sqlite3
```

Where are the log files saved?

Log file for scheduler

The scheduling application, "PausitLauncher.exe", writes error log entries to the following file:

```
%AppData%\Pausit\Pausit.log
```

Log file for player and settings

The application for 3D content, "Pausit.exe", writes log entries to the following file:

```
%HomePath%\AppData\LocalLow\Pausit AB\Pausit\output_log.txt
```

Manual

The manual for Pausit is available at: <https://pausit.se/support/>